

CUSTOMER SERVICE BULLETIN

Radio Shack® CUSTOMER SERVICE BULLETIN

400 Atrium—One Tandy Center, Fort Worth, Texas 76102

Bulletin No.	4505-17
Description	Accounts Payable
Model	Model II
Stock No.	26-4505 Version 1.0/2.0
Date	Jan. 27, 1982
Page 1 of	1

Problem

When using the Print Checks option, the user is not able to disable the printing of check numbers on the checks.

Solution

The problem is corrected by following the steps listed below.

1. Backup the diskette(s) and make the changes on the Backup copy of the program.
2. In BASIC load the program by typing LOAD"APCHECKS/BAS".
3. Make the following corrections:

CHANGES (Retype the line or refer to the Edit section of the owners manual)

TO ELIMINATE CHECK NUMBER FROM PRINTING ON STUB:

Old Line: 2410 LPRINTL1\$:LPRINT;NA\$;TAB(61)LC:LPRINTL1\$:LPRINTL1\$:RETURN
New Line: 2410 LPRINTL1\$:LPRINT;NA\$:LPRINTL1\$:LPRINTL1\$:RETURN

TO ELIMINATE CHECK NUMBER FROM PRINTING ON CHECK:

Old Line: 2515 LPRINTL1\$:LPRINTL1\$:LPRINTTAB(61)LC:LPRINTL1\$:LPRINTL1\$
New Line: 2515 LPRINTL1\$:LPRINTL1\$:LPRINTL1\$:LPRINTL1\$:LPRINTL1\$

4. Type SAVE"APCHECKS/BAS" to save the changes in the program.
5. At TRSDOS READY, make a backup copy of the corrected diskette.